



[Knowledgebase](#) > [Website Hosting](#) > [Redis Object Cache Setup in WordPress](#)

# Redis Object Cache Setup in WordPress

Binh Pham - 2026-04-13 - [Website Hosting](#)

## How to Enable Redis Object Cache on a WordPress site


This guide covers the process of enabling Redis object caching for a cPanel user on a LiteSpeed web server. It includes enabling Redis via the LiteSpeed WHM plugin, verifying the service is running, and configuring the LiteSpeed Cache WordPress plugin to connect to it.

### Prerequisites

- LiteSpeed Web Server
- Litespeed WHM Plugin
- CloudLinux
- PHP Redis extension enabled

### Step 1: Navigate to Cache Redis for Users

1. Login to WHM as root
2. In the left navigation, go to LiteSpeed Web Server
3. Click Cache Redis for Users



1.

### Step 2: Enable Redis for the Users

1. Locate the cPanel username in the list
2. In the Service MB column, the default is 64MB. Adjust if needed.
3. Click the Setup Icon (Yellow Box)



1.

4. It may take a bit to install. Afterward, enable the Redis service on the user by clicking the grey cog.

5. It should then be enabled with a green play icon



1.

### Step 3: Enable Redis Cache in LiteSpeed Cache Plugin

1. Login to your WordPress admin dashboard
2. Install LiteSpeed Cache Plugin
3. Navigate to LiteSpeed Cache > Cache > Object
4. Set the following settings and then **save**:
  1. Object Cache: **ON**
  2. Method: **Redis**
  3. Host: **/tmp/redis.sock**
  4. Port: **0**

<b>Object Cache</b>	<input type="radio"/> OFF <input checked="" type="radio"/> ON
Use external object cache functionality. <a href="#">Learn More</a>	
<b>Status</b>	Memcached Extension : <span style="color: green;">Enabled</span> Redis Extension : <span style="color: green;">Enabled</span> Connection Test: <span style="color: green;">Passed</span> <a href="#">Learn More</a>
<b>Method</b>	<input type="radio"/> Memcached <input checked="" type="radio"/> Redis
<b>Host</b>	<input type="text" value="/tmp/redis.sock"/> Your Memcached/ <a href="#">LSMCD</a> /Redis Hostname or IP address. If you are using a UNIX socket, Host should be set to <code>/path/to/memcached.sock</code>
<b>Port</b>	<input type="text" value="0"/> Default port for Memcached is <code>11211</code> . Default port for Redis is <code>6379</code> . If you are using a UNIX socket, Port should be set to <code>0</code>

1.

1. If your Redis extension does not show as enabled, make sure to enable the extension first in your PHP.